



## CISCO UNIFIED COMMUNICATIONS MANAGER 7.1(2) TCP AND UDP PORT USAGE

This document provides a list of the TCP and UDP ports that Cisco Unified Communications Manager 7.1(2) uses for intracluster connections and for communications with external applications or devices. It provides important information for the configuration of firewalls, Access Control Lists (ACLs), and quality of service (QoS) on a network when an IP Communications solution is implemented.

**Note:** Cisco has not verified all possible configuration scenarios for these ports. If you are having configuration problems using this list, contact Cisco technical support for assistance.

While virtually all protocols are bidirectional, this document gives directionality from the session originator perspective. In some cases, the administrator can manually change the default port numbers, though Cisco does not recommend this as a best practice. Be aware that Cisco Unified Communications Manager opens several ports strictly for internal use.

Ports in this document apply specifically to Cisco Unified Communications Manager Release 7.1(2). Some ports change from one release to another, and future releases may introduce new ports. Therefore, make sure that you are using the correct version of this document for the version of Cisco Unified Communications Manager that is installed.

Installing Cisco Unified Communications Manager 7.1(2) software automatically installs the following network services for serviceability and activates them by default:

- Cisco Log Partition Monitoring (to monitor and purge the common partition; no custom common port used)
- Cisco Trace Collection Service (see table for TCTS port usage)
- Cisco RIS Data Collector (see table for RIS server port usage)
- Cisco AMC Service (see table for AMC port usage)

Configuration of firewalls, ACLs, or QoS will vary depending on topology, placement of telephony devices and services relative to the placement of network security devices, and which applications and telephony extensions are in use. Also, bear in mind that ACLs vary in format with different devices and versions.

**Note:** You can also configure Multicast MOH ports in Cisco Unified CM Administration. Because the administrator specifies the actual port values, this document does not contain port values for multicast MOH.

**Note:** The Ephemeral (see tables below) port range for the system is 32768 – 61000.



From (Sender)	To (Listener)	Dest. Port	Purpose
---------------	---------------	------------	---------

Intracuster Ports Between Cisco Unified Communications Managers			
Endpoint	Unified CM	514 / UDP	System logging service
Unified CM	RTMT	1090, 1099 / TCP	Cisco AMC Service for RTMT performance monitors, data collection, logging, and alerting
Unified CM (DB)	Unified CM (DB)	1500, 1501 / TCP	Database connection (1501 / TCP is the secondary connection)
Unified CM (DB)	Unified CM (DB)	1515 / TCP	Database replication between nodes during installation
Cisco Extended Functions (QRT)	Unified CM (DB)	2552 / TCP	Allows subscribers to receive Cisco Unified Communications Manager database change notification
Unified CM	Unified CM	2551 / TCP	Intracuster communication between Cisco Extended Services for Active/Backup determination
Unified CM (RIS)	Unified CM (RIS)	2555 / TCP	Real-time Information Services (RIS) database server
Unified CM (RTMT/AMC/SOAP)	Unified CM (RIS)	2556 / TCP	Real-time Information Services (RIS) database client for Cisco RIS
Unified CM (DRF)	Unified CM (DRF)	4040 / TCP	DRF Master Agent
Unified CM (Tomcat)	Unified CM (SOAP)	5007 / TCP	SOAP monitor
Unified CM (RTMT)	Unified CM (TCTS)	Ephemeral / TCP	Cisco Trace Collection Tool Service (TCTS) -- the backend service for RTMT Trace & Log Central (TLC)
Unified CM (Tomcat)	Unified CM (TCTS)	7000 then Ephemeral (Linux) / TCP	This port is used for communication between Cisco Trace Collection Tool Service and Cisco Trace Collection servlet.
Intracuster Ports Between Cisco Unified Communications Managers (continued)			
Unified CM	Certificate Manager	7070 / TCP	Certificate Manager service



Unified CM (DB)	Unified CM (CDLM)	8001 / TCP	Client database change notification
Unified CM (SDL)	Unified CM (SDL)	8002 / TCP	Intracluster communication service
Unified CM (SDL)	Unified CM (SDL)	8003 / TCP	Intracluster communication service (to CTI)
Unified CM	CMI Manager	8004 / TCP	Intracluster communication between Cisco Unified Communications Manager and CMI Manager
Unified CM (Tomcat)	Unified CM (Tomcat)	8005 / TCP	Internal listening port used by Tomcat shutdown scripts
Unified CM (IPSec)	Unified CM (IPSec)	8500 / TCP and UDP	Intracluster replication of system data by IPSec Cluster Manager
Unified CM (RIS)	Unified CM (RIS)	8888 - 8889 / TCP	RIS Service Manager status request and reply

Common Service Ports			
Endpoint	Unified CM	7	Internet Control Message Protocol (ICMP) This protocol number carries echo-related traffic. It does not constitute a port as indicated in the column heading.
Unified CM	Endpoint		
Unified CM	Endpoint	22 / TCP	Secure FTP service, SSH access
Endpoint	Unified CM (DNS Server)	Ephemeral / UDP	Cisco Unified Communications Manager acting as a DNS server or DNS client (Note: Cisco recommends that Cisco Unified Communications Manager not act as a DNS server and that all IP telephony applications and endpoints use static IP addresses instead of hostnames.)
Unified CM	DNS Server		
Endpoint	Unified CM (DHCP Server)	67 / UDP	Cisco Unified Communications Manager acting as a DHCP server (Note: Cisco does not recommend running DHCP server on Cisco Unified Communications Manager.)



Common Service Ports (continued)			
Unified CM	DHCP Server	68 / UDP	Cisco Unified Communications Manager acting as a DHCP client (Note: Cisco does not recommend running DHCP client on Cisco Unified Communications Manager. Configure Cisco Unified Communications Manager with static IP addresses instead.)
Endpoint or Gateway	Unified CM	69, 6969, then Ephemeral / UDP	Trivial File Transfer Protocol (TFTP) service to phones and gateways
Unified CM	NTP Server	123 / UDP	Network Time Protocol (NTP)
SNMP Server	Unified CM	161 / UDP	SNMP service response (requests from management applications)
SNMP Server	Unified CM	199 / TCP	Native SNMP agent listening port for SMUX support
Unified CM	Unified CM	6161 / UDP	Used for communication between Master Agent and Native Agent to process Native agent MIB requests
Unified CM	Unified CM	6162 / UDP	Used for communication between Master Agent and Native Agent to forward notifications generated from Native Agent
Unified CM	Unified CM	6666 / UDP	Netdump server
Centralized TFTP	Alternate TFTP	6970 / TCP	Centralized TFTP File Locator Service
Unified CM	Unified CM	7161 / TCP	Used for communication between SNMP Master Agent and subagents
SNMP Server	Unified CM	7999 / TCP	Cisco Discovery Protocol (CDP) agent communicates with CDP executable
Unified CM	Unified CM	9050 / TCP	Service CRS requests through the TAPS residing on Cisco Unified Communications Manager
Unified CM	Unified CM	61441 / UDP	Cisco Unified Communications Manager applications send out alarms to this port via UDP. Cisco Unified Communications Manager MIB agent listens on this port and generates SNMP traps per Cisco Unified Communications Manager MIB definition.
Unified CM	Unified CM	Ephemeral	Provide trunk-based SIP services



Between Cisco Unified Communications Manager and LDAP Directory			
Unified CM	External Directory	Ephemeral/ TCP	Lightweight Directory Access Protocol (LDAP) query to external directory (Active Directory, Netscape Directory)
External Directory	Unified CM		

Web Requests from CCMAdmin or CCMUser to Cisco Unified Communications Manager			
Workstation	Unified CM	22/TCP	SSH CLI access
Browser	Unified CM	80, 8080 / TCP	Hypertext Transport Protocol (HTTP)
Browser	Unified CM	443, 8443 / TCP	Hypertext Transport Protocol over SSL (HTTPS)
Browser or CLI	Unified CM	2355, 2356 / TCP	Log audit events from the CLI and Web applications

Web Requests from Cisco Unified Communications Manager to Phone			
Unified CM <ul style="list-style-type: none"> <li>▪ QRT</li> <li>▪ RTMT</li> <li>▪ Find and List Phones page</li> <li>▪ Phone Configuration page</li> </ul>	Phone	80 / TCP	Hypertext Transport Protocol (HTTP)

Signaling, Media, and Other Communication Between Phones and Cisco Unified Communications Manager			
Phone	Unified CM (TFTP)	69, then Ephemeral / UDP	Trivial File Transfer Protocol (TFTP) used to download firmware and configuration files
Phone	Unified CM	8080 / TCP	Phone URLs for XML applications, authentication, directories, services, and so on. You can configure these ports on a per-service basis.
Phone	Unified CM	2000 / TCP	Skinny Client Control Protocol (SCCP)



Phone	Unified CM	2443 / TCP	Secure Skinny Client Control Protocol (SCCPS)
<b>Signaling, Media, and Other Communication Between Phones and Cisco Unified Communications Manager (continued)</b>			
Phone	Unified CM (CAPF)	3804 / TCP	Certificate Authority Proxy Function (CAPF) listening port for issuing Locally Significant Certificates (LSCs) to IP phones
Phone	Unified CM	5060 / TCP and UDP	Session Initiation Protocol (SIP) phone
Unified CM	Phone		
Phone	Unified CM	5061 TCP and UDP	Secure Session Initiation Protocol (SIPS) phone
Unified CM	Phone		
IP VMS	Phone	16384 - 32767 / UDP	Real-Time Protocol (RTP), Secure Real-Time Protocol (SRTP) (Note: Cisco Unified Communications Manager only uses 24576-32767 although other devices use the full range.)
Phone	IP VMS		

<b>Signaling, Media, and Other Communication Between Gateways and Cisco Unified Communications Manager</b>			
Gateway	Unified CM	47, 50, 51	Generic Routing Encapsulation (GRE), Encapsulating Security Payload (ESP), Authentication Header (AH). These protocols numbers carry encrypted IPSec traffic. They do not constitute a port as indicated in the column heading.
Unified CM	Gateway		
Gateway	Unified CM	500 / UDP	Internet Key Exchange (IKE) for IP Security protocol (IPSec) establishment
Unified CM	Gateway		
Gateway	Unified CM (TFTP)	69, then Ephemeral / UDP	Trivial File Transfer Protocol (TFTP)
Gatekeeper	Unified CM	1719 / UDP	Gatekeeper (H.225) RAS
Gateway	Unified CM	1720 / TCP	H.225 signaling services for H.323 gateways and Intercluster Trunk (ICT)
Unified CM	Gateway		



Signaling, Media, and Other Communication Between Gateways and Cisco Unified Communications Manager (continued)			
Gateway	Unified CM	Ephemeral / TCP	H.225 signaling services on gatekeeper-controlled trunk
Unified CM	Gateway		
Gateway	Unified CM	Ephemeral / TCP	H.245 signaling services for establishing voice, video, and data
Unified CM	Gateway		
Gateway	Unified CM	2000 / TCP	Skinnny Client Control Protocol (SCCP)
Gateway	Unified CM	2001 / TCP	Upgrade port for 6608 gateways with Cisco Unified CM deployments
Gateway	Unified CM	2002 / TCP	Upgrade port for 6624 gateways with Cisco Unified CM deployments
Gateway	Unified CM	2427 / UDP	Media Gateway Control Protocol (MGCP) gateway control
Gateway	Unified CM	2428 / TCP	Media Gateway Control Protocol (MGCP) backhaul
Gateway	Unified CM	5060 / TCP and UDP	Session Initiation Protocol (SIP) gateway and Intercluster Trunk (ICT)
Unified CM	Gateway		
Gateway	Unified CM	5061 / TCP and UDP	Secure Session Initiation Protocol (SIPS) gateway and Intercluster Trunk (ICT)
Unified CM	Gateway		
Gateway	Unified CM	16384 - 32767 / UDP	Real-Time Protocol (RTP), Secure Real-Time Protocol (SRTP) (Note: Cisco Unified Communications Manager only uses 24576-32767 although other devices use the full range.)
Unified CM	Gateway		



Communication Between Applications and Cisco Unified Communications Manager			
CTL Client	Unified CM CTL Provider	2444 / TCP	Certificate Trust List (CTL) provider listening service in Cisco Unified Communications Manager
Cisco Unified Communications App	Unified CM	2748 / TCP	CTI application server
Cisco Unified Communications App	Unified CM	2749 / TCP	TLS connection between CTI applications (JTAPI/TSP) and CTIManager
Cisco Unified Communications App	Unified CM	2789 / TCP	JTAPI application server
Unified CM Assistant Console	Unified CM	2912 / TCP	Cisco Unified Communications Manager Assistant server (formerly IPMA)
Unified CM Attendant Console	Unified CM	1103 -1129 / TCP	Cisco Unified Communications Manager Attendant Console (AC) JAVA RMI Registry server
Unified CM Attendant Console	Unified CM	1101 / TCP	RMI server sends RMI callback messages to clients on these ports.
Unified CM Attendant Console	Unified CM	1102 / TCP	Attendant Console (AC) RMI server bind port -- RMI server sends RMI messages on these ports.
Unified CM Attendant Console	Unified CM	3223 / UDP	Cisco Unified Communications Manager Attendant Console (AC) server line state port receives ping and registration message from, and sends line states to, the attendant console server.
Unified CM Attendant Console	Unified CM	3224 / UDP	Cisco Unified Communications Manager Attendant Console (AC) clients register with the AC server for line and device state information.
Unified CM Attendant Console	Unified CM	4321 / UDP	Cisco Unified Communications Manager Attendant Console (AC) clients register to the AC server for call control.
Cisco Unified Communications App	Unified CM	8443 / TCP	AXL / SOAP API for programmatic reads from or writes to the Cisco Unified Communications Manager database that third parties such as billing or telephony management applications use.

Communication Between CTL Client and Firewalls			
CTL Client	TLS Proxy Server	2444 / TCP	Certificate Trust List (CTL) provider listening service in an ASA firewall





Special Ports on HP Servers			
Endpoint	HP SIM	2301 / TCP	HTTP port to HP agent
Endpoint	HP SIM	2381 / TCP	HTTPS port to HP agent
Endpoint	Compaq Mgmt Agent	25375, 25376, 25393 / UDP	COMPAQ Management Agent extension (cmaX)
Endpoint	HP SIM	50000 - 50004 / TCP	HTTPS port to HP SIM



## Glossary

**AXL / SOAP:** Cisco Unified Communications XML Layer / Simple Object Access Protocol – API that applications use to read from or write to the Cisco Unified Communications Manager database.

**CAPF:** Certificate Authority Proxy Function – Used to load X.509 digital certificates into IP phones.

**CDLM:** Cisco Database Layer Monitor – Used to synchronize the database with what is running in active memory.

**CTI:** Computer Telephony Integration – Provides a link between telephone systems and computers to facilitate incoming and outgoing call handling and control; the physical link between a telephone and server.

**CTL Client:** Certificate Trust List Client – Application that creates the Certificate Trust List that gets loaded into IP phones. This plug-in comes with Cisco Unified Communications Manager and can be run on any computer that a) has IP connectivity to all Cisco Unified Communications Managers in the cluster and b) has a USB port.

**DRF:** Disaster Recovery Framework

**Ephemeral Ports:** In virtually all cases, source ports are ephemeral, meaning random within a specified range. When an outgoing request is made, the application solicits the host device for a port from its ephemeral pool. In a few cases, the destination port is also ephemeral, meaning that both the source and destination ports are random.

**JTAPl:** Java Telephony Application Program Interface – Sun Microsystems telephony programming interface for Java. It provides a set of classes and interfaces that provide access to call control and telephony device control as well as media and administrative services.

**LDAP:** Lightweight Directory Access Protocol – Used to validate user credentials against the designated directory service.

**LDAPS:** Lightweight Directory Access Protocol over TLS/SSL – Used to validate user credentials against the designated directory service.

**IP VMS:** Cisco IP Voice Media Streaming Application – Used for music on hold, annunciator, conference bridge, media termination point (MTP), and so on.

**RIS:** Real-Time Information Services database – Used by the Real-Time Monitoring Tool (RTMT) in the Serviceability application.

**RTMT:** Real-Time Monitoring Tool

**SDL:** Signal Distribution Layer Link – Used for intracluster communications.

**SOAP:** Simple Object Access Protocol

**TCTS:** Trace Collection Tool Service – The backend service for RTMT Trace & Log Central (TLC)

**TFTP:** Trivial File Transfer Protocol – Used to load firmware and configurations into phones, gateways, and so on.

**Tomcat:** Web server



## References

### Firewall Application Inspection Guides

#### ASA Series

[http://www.cisco.com/en/US/products/ps6120/tsd\\_products\\_support\\_series\\_home.html](http://www.cisco.com/en/US/products/ps6120/tsd_products_support_series_home.html)

#### PIX 6.3 Application Inspection Configuration Guide

<http://www.cisco.com/en/US/docs/security/pix/pix63/configuration/guide/fixup.html>

#### PIX 7.1 Application Inspection Configuration Guide

<http://www.cisco.com/en/US/docs/security/asa/asa71/configuration/guide/inspect.html>

#### FWSM 3.1 Application Inspection Configuration Guide

[http://www.cisco.com/en/US/docs/security/fwsm/fwsm31/configuration/guide/inspct\\_f.html](http://www.cisco.com/en/US/docs/security/fwsm/fwsm31/configuration/guide/inspct_f.html)

#### IOS 12.4 Configuring Context-Based Access Control

[http://www.cisco.com/en/US/products/ps6350/products\\_configuration\\_guide\\_chapter09186a00804a41c5.html](http://www.cisco.com/en/US/products/ps6350/products_configuration_guide_chapter09186a00804a41c5.html)

#### IOS 12.4 Configuring IP Access Lists

[http://www.cisco.com/en/US/products/ps6350/products\\_configuration\\_guide\\_chapter09186a0080430e5b.html](http://www.cisco.com/en/US/products/ps6350/products_configuration_guide_chapter09186a0080430e5b.html)

### IP Telephony Configuration and Port Utilization Guides

#### Cisco CRS 4.0 (IP IVR and IPCC Express) Port Utilization Guide

[http://www.cisco.com/en/US/products/sw/custcosw/ps1846/products\\_installation\\_and\\_configuration\\_guides\\_list.html](http://www.cisco.com/en/US/products/sw/custcosw/ps1846/products_installation_and_configuration_guides_list.html)

#### Port Utilization Guide for Cisco ICM/IPCC Enterprise and Hosted Editions

[http://www.cisco.com/en/US/products/sw/custcosw/ps1001/products\\_installation\\_and\\_configuration\\_guides\\_list.html](http://www.cisco.com/en/US/products/sw/custcosw/ps1001/products_installation_and_configuration_guides_list.html)

#### Cisco ICM / IPCC Enterprise and Hosted Editions 7.1(2)(0) Port Utilization Guide

[http://www.cisco.com/application/pdf/en/us/quest/products/ps1001/c1067/ccmigration\\_09186a00805abe34.pdf](http://www.cisco.com/application/pdf/en/us/quest/products/ps1001/c1067/ccmigration_09186a00805abe34.pdf)

#### Cisco Unified Communications Manager Express Security Guide to Best Practices

[http://www.cisco.com/en/US/netsol/ns340/ns394/ns165/ns391/networking\\_solutions\\_design\\_guidance09186a00801f8e30.html](http://www.cisco.com/en/US/netsol/ns340/ns394/ns165/ns391/networking_solutions_design_guidance09186a00801f8e30.html)

#### Cisco Unity Express Security Guide to Best Practices

[http://www.cisco.com/en/US/netsol/ns340/ns394/ns165/ns391/networking\\_solutions\\_design\\_guidance09186a00801f8e31.html#wp41149](http://www.cisco.com/en/US/netsol/ns340/ns394/ns165/ns391/networking_solutions_design_guidance09186a00801f8e31.html#wp41149)

### IETF TCP/UDP Port Assignment List

#### Internet Assigned Numbers Authority (IANA) IETF assigned Port List

<http://www.iana.org/assignments/port-numbers>



**Corporate Headquarters**

Cisco Systems, Inc.  
170 West Tasman Drive  
San Jose, CA 95134-1706  
USA  
www.cisco.com  
Tel: 408 526-4000  
800 553-NETS (6387)  
Fax: 408 526-4100

**European Headquarters**

Cisco Systems International  
BV  
Haarlerbergpark  
Haarlerbergweg 13-19  
1101 CH Amsterdam  
The Netherlands  
www-europe.cisco.com  
Tel: 31 0 20 357 1000  
Fax: 31 0 20 357 1100

**Americas Headquarters**

Cisco Systems, Inc.  
170 West Tasman Drive  
San Jose, CA 95134-1706  
USA  
www.cisco.com  
Tel: 408 526-7660  
Fax: 408 527-0883

**Asia Pacific Headquarters**

Cisco Systems, Inc.  
168 Robinson Road  
#28-01 Capital Tower  
Singapore 068912  
www.cisco.com  
Tel: +65 6317 7777  
Fax: +65 6317 7799

Cisco Systems has more than 200 offices in the following countries and regions. Addresses, phone numbers, and fax numbers are listed on **the Cisco Web site at [www.cisco.com/go/offices](http://www.cisco.com/go/offices).**

Argentina • Australia • Austria • Belgium • Brazil • Bulgaria • Canada • Chile • China PRC • Colombia • Costa Rica • Croatia • Cyprus  
Czech Republic • Denmark • Dubai, UAE • Finland • France • Germany • Greece • Hong Kong SAR • Hungary • India • Indonesia • Ireland  
Israel • Italy • Japan • Korea • Luxembourg • Malaysia • Mexico • The Netherlands • New Zealand • Norway • Peru • Philippines • Poland  
Portugal • Puerto Rico • Romania • Russia • Saudi Arabia • Scotland • Singapore • Slovakia • Slovenia • South Africa • Spain • Sweden  
Switzerland • Taiwan • Thailand • Turkey • Ukraine • United Kingdom • United States • Venezuela • Vietnam • Zimbabwe

CCDE, CCSI, CCENT, Cisco Eos, Cisco HealthPresence, the Cisco logo, Cisco Lumin, Cisco Nexus, Cisco Nurse Connect, Cisco Stackpower, Cisco StadiumVision, Cisco TelePresence, Cisco WebEx, DCE, and Welcome to the Human Network are trademarks; Changing the Way We Work, Live, Play, and Learn and Cisco Store are service marks; and Access Registrar, Aironet, AsyncOS, Bringing the Meeting To You, Catalyst, CCDA, CCDP, CCIE, CCIP, CCNA, CCNP, CCSP, CCVP, Cisco, the Cisco Certified Internetwork Expert logo, Cisco IOS, Cisco Press, Cisco Systems, Cisco Systems Capital, the Cisco Systems logo, Cisco Unity, Collaboration Without Limitation, EtherFast, EtherSwitch, Event Center, Fast Step, Follow Me Browsing, FormShare, GigaDrive, HomeLink, Internet Quotient, IOS, iPhone, iQuick Study, IronPort, the IronPort logo, LightStream, Linksys, MediaTone, MeetingPlace, MeetingPlace Chime Sound, MGX, Networkers, Networking Academy, Network Registrar, PCNow, PIX, PowerPanels, ProConnect, ScriptShare, SenderBase, SMARTnet, Spectrum Expert, StackWise, The Fastest Way to Increase Your Internet Quotient, TransPath, WebEx, and the WebEx logo are registered trademarks of Cisco Systems, Inc. and/or its affiliates in the United States and certain other countries.

All other trademarks mentioned in this document or website are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (0903R)

*Cisco Unified Communications Manager 7.1(2) TCP and UDP Port Usage*  
Copyright © 2009 Cisco Systems, Inc. All rights reserved.